



# HOW TO INSTALL LIBRARY AND KITS UPDATE TO THE PEARL MIMIC PRO

1. First start with an **empty USB 2.0 flash drive**. For these updates the smaller sized USB flash drive can be used. When loading a **Full Sound library**, the **size of USB flash drive must be at least 16 GB or more**.
2. **UnZIP update file to the flash drive**. Usually the name will be similar to “Mimic\_Lib\_Update\_July10\_2017.zip” except the date will change with each new update.



3. After it is complete the folder named **“Mimic\_Factory.lib”** should be on a flash drive. If that folder is not on the flash drive, then the folder was unZIPped to different location. You must locate the folder on your computer and put it on the flash drive.



4. Turn the Mimic Pro **Off** and insert USB flash drive into the Mimic Pro USB port.
5. Turn the Mimic Pro **On**. Go to **Settings** and press the “**Import Instruments from USB Stick**” button.



6. Select the **"Mimic\_Factory.lib"** on the left tab, press the **"Import"** button in the left bottom corner and wait 3-5 seconds **after** the process is complete.



7. Press the **Home** button.
8. Turn the Mimic Pro **Off** and eject the USB flash drive from the Mimic Pro.
9. Turn the Mimic Pro **On** and explore your new update.